

Arm® Streamline


Version 8.1

Target Setup Guide for Linux

Non-Confidential

Issue 00

Copyright © 2021–2022 Arm Limited (or its affiliates). 101814_0801_00_en All rights reserved.



Arm[®] Streamline

Target Setup Guide for Linux

Copyright © 2021–2022 Arm Limited (or its affiliates). All rights reserved.

Release information

Document history

Issue	Date	Confidentiality	Change
0708-00	20 August 2021	Non-Confidential	New document for v7.8
0709-00	18 November 2021	Non-Confidential	New document for v7.9
0800-00	18 February 2022	Non-Confidential	New document for v8.0
0801-00	20 May 2022	Non-Confidential	New document for v8.1

Proprietary Notice

This document is protected by copyright and other related rights and the practice or implementation of the information contained in this document may be protected by one or more patents or pending patent applications. No part of this document may be reproduced in any form by any means without the express prior written permission of Arm. No license, express or implied, by estoppel or otherwise to any intellectual property rights is granted by this document unless specifically stated.

Your access to the information in this document is conditional upon your acceptance that you will not use or permit others to use the information for the purposes of determining whether implementations infringe any third party patents.

THIS DOCUMENT IS PROVIDED "AS IS". ARM PROVIDES NO REPRESENTATIONS AND NO WARRANTIES, EXPRESS, IMPLIED OR STATUTORY, INCLUDING, WITHOUT LIMITATION, THE IMPLIED WARRANTIES OF MERCHANTABILITY, SATISFACTORY QUALITY, NON-INFRINGEMENT OR FITNESS FOR A PARTICULAR PURPOSE WITH RESPECT TO THE DOCUMENT. For the avoidance of doubt, Arm makes no representation with respect to, has undertaken no analysis to identify or understand the scope and content of, third party patents, copyrights, trade secrets, or other rights.

This document may include technical inaccuracies or typographical errors.

TO THE EXTENT NOT PROHIBITED BY LAW, IN NO EVENT WILL ARM BE LIABLE FOR ANY DAMAGES, INCLUDING WITHOUT LIMITATION ANY DIRECT, INDIRECT, SPECIAL, INCIDENTAL, PUNITIVE, OR CONSEQUENTIAL DAMAGES, HOWEVER CAUSED AND

REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF ANY USE OF THIS DOCUMENT, EVEN IF ARM HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

This document consists solely of commercial items. You shall be responsible for ensuring that any use, duplication or disclosure of this document complies fully with any relevant export laws and regulations to assure that this document or any portion thereof is not exported, directly or indirectly, in violation of such export laws. Use of the word "partner" in reference to Arm's customers is not intended to create or refer to any partnership relationship with any other company. Arm may make changes to this document at any time and without notice.

This document may be translated into other languages for convenience, and you agree that if there is any conflict between the English version of this document and any translation, the terms of the English version of the Agreement shall prevail.

The Arm corporate logo and words marked with ® or ™ are registered trademarks or trademarks of Arm Limited (or its subsidiaries) in the US and/or elsewhere. All rights reserved. Other brands and names mentioned in this document may be the trademarks of their respective owners. Please follow Arm's trademark usage guidelines at https://www.arm.com/company/policies/trademarks.

Copyright © 2021–2022 Arm Limited (or its affiliates). All rights reserved.

Arm Limited. Company 02557590 registered in England.

110 Fulbourn Road, Cambridge, England CB1 9NJ.

(LES-PRE-20349)

Confidentiality Status

This document is Non-Confidential. The right to use, copy and disclose this document may be subject to license restrictions in accordance with the terms of the agreement entered into by Arm and the party that Arm delivered this document to.

Unrestricted Access is an Arm internal classification.

Product Status

The information in this document is Final, that is for a developed product.

Feedback

Arm® welcomes feedback on this product and its documentation. To provide feedback on the product, create a ticket on https://support.developer.arm.com

To provide feedback on the document, fill the following survey: https://developer.arm.com/documentation-feedback-survey.

Inclusive language commitment

Arm values inclusive communities. Arm recognizes that we and our industry have used language that can be offensive. Arm strives to lead the industry and create change.

We believe that this document contains no offensive language. To report offensive language in this document, email terms@arm.com.

Contents

1 Introduction	6
1.1 Conventions	6
1.2 Other information	7
2 Target Setup	8
2.1 Introduction to using Streamline with a Linux device	8
2.2 Compiling your application	8
2.3 Set up your target	9
2.4 System requirements for SPE support	11
2.5 gatord	11
2.5.1 gatord command-line options	12
2.6 Capture data locally on a target	15
2.7 Support for Arm CoreLink tools	16
2.8 Using Streamline with Arm NN	16
3 Customize your Streamline report	18
3.1 Add a CPU to Streamline	18
3.2 Add an uncore peripheral to Streamline	18
3.3 Contributing CPU and peripheral support	19
4 Troubleshooting Common Arm Streamline Issues (Linux)	20
4.1 Troubleshooting target connection issues	20
4.2 Troubleshooting gatord issues	21
5 Advanced target setup information (Linux)	22
5.1 Kernel configuration menu options	22
5.2 Profile the Linux kernel	23
5.3 Build gatord yourself	24
5.4 Add support to gatord for a new CPU or perf PMU	24

1 Introduction

This document describes how to set up a Linux device for profiling with Arm® Streamline.

1.1 Conventions

The following subsections describe conventions used in Arm documents.

Glossary

The Arm Glossary is a list of terms used in Arm documentation, together with definitions for those terms. The Arm Glossary does not contain terms that are industry standard unless the Arm meaning differs from the generally accepted meaning.

See the Arm® Glossary for more information: developer.arm.com/glossary.

Typographic conventions

Arm documentation uses typographical conventions to convey specific meaning.

Convention	Use
italic	Citations.
bold	Interface elements, such as menu names.
	Signal names.
	Terms in descriptive lists, where appropriate.
monospace	Text that you can enter at the keyboard, such as commands, file and program names, and source code.
monospace bold	Language keywords when used outside example code.
monospace <u>underline</u>	A permitted abbreviation for a command or option. You can enter the underlined text instead of the full command or option name.
<and></and>	Encloses replaceable terms for assembler syntax where they appear in code or code fragments.
	For example:
	MRC p15, 0, <rd>, <crn>, <opcode_2></opcode_2></crn></rd>
SMALL CAPITALS	Terms that have specific technical meanings as defined in the Arm® Glossary. For example, IMPLEMENTATION DEFINED, IMPLEMENTATION SPECIFIC, UNKNOWN, and UNPREDICTABLE.
Caution	Recommendations. Not following these recommendations might lead to system failure or damage.
Warning	Requirements for the system. Not following these requirements might result in system failure or damage.
Danger	Requirements for the system. Not following these requirements will result in system failure or damage.

Convention	Use
Note	An important piece of information that needs your attention.
- Tip	A useful tip that might make it easier, better or faster to perform a task.
Remember	A reminder of something important that relates to the information you are reading.

1.2 Other information

See the Arm website for other relevant information.

- Arm® Developer.
- Arm® Documentation.
- Technical Support.
- Arm® Glossary.

2 Target Setup

This chapter explains how to set up your target and host devices ready to use Streamline for application or system profiling.

2.1 Introduction to using Streamline with a Linux device

Streamline supports system-wide profiling of applications running on Linux-based embedded devices. Analyze the behavior of the system hardware by selecting the required Arm CPU or Arm[®] Mali[™] GPU hardware performance counters for your scenario.



Some Streamline features are license-managed. For more information, see Licenses in the Arm Streamline User Guide.

This analysis can be supplemented by connecting power measurement probes, such as the Arm Energy Probe or National Instruments DAQ, to provide accurate measurement of system energy use. To provide more context to the analysis, you can use software annotations in Arm software libraries, such as the Mali GPU OpenCL device driver.

Use the information in this guide to prepare your Linux target, ready for profiling with Streamline. Then refer to the Arm Streamline User Guide for details about working with Streamline.

2.2 Compiling your application

When building executables for profiling with Streamline, it is best practice to use these compiler options when using GCC or Clang.

-g

Enable the debug symbols necessary for quality analysis reports.

-fno-inline

Disable inlining and substantially improve the call path quality.

-fno-omit-frame-pointer

Compile your EABI images and libraries with frame pointers. This option enables Streamline to record the call stack with each sample taken.

-mno-omit-leaf-frame-pointer

Keep the frame pointer in leaf functions.

-marm

When building for AArch32, if GCC was compiled with the --with-mode=thumb option enabled, this option is required. Using the --with-mode=thumb option without -marm breaks call stack unwinding in Streamline.

Call stack unwinding

You must provide extra compiler flags for call stack unwinding to work.

For AArch64 applications, the flag <code>-fno-omit-frame-pointer</code> is required. We also strongly recommend using <code>-mno-omit-leaf-frame-pointer</code> to prevent samples in leaf functions incorrectly listing their grand-parent function as their parent. The <code>-mno-omit-leaf-frame-pointer</code> flag is not supported by Clang.

For AArch32 applications, the flags -fno-omit-frame-pointer, -marm, and -mapcs-frame are required.



Streamline does not support call stack unwinding for T32 (Thumb®) code. It also does not support call stack unwinding for code that Arm® Compiler version 5 and earlier (armcc) generates.

2.3 Set up your target

To profile your software using Streamline, you must have a suitably configured Linux kernel and gatord running on an Arm®-based hardware target.

Before you begin

- Download Arm Development Studio. See Arm Development Studio Downloads.
- Install Arm Development Studio. Follow the instructions in the Arm Development Studio Getting Started Guide.
- If you intend to use the Statistical Profiling Extension (SPE) in Streamline, there are some additional system requirements. Refer to System requirements for SPE support.

Procedure

1. Validate the Linux kernel configuration.

The kernel configuration must include the options that are described in Kernel configuration menu options. You can usually find your kernel configuration in /proc/config.gz. If this file is not visible, depending how your system is configured, you can create it by running:

sudo modprobe configs

The following command confirms whether an option is enabled:

```
zcat /proc/config.gz | grep <OPTION>
```

For example:

```
zcat /proc/config.gz | grep CONFIG_PROFILING
```

2. Install gatord on your target.

Two pre-built gatord binaries are available:

- For Armv7 targets, and Armv8 targets that support AArch32 execution state.
- For Armv8 AArch64 targets.

The pre-built gatord binaries are available from the Arm Development Studio installation directory <install directory>/sw/streamline/bin/linux/

The source code for gatord is available from the following locations:

- The Arm Development Studio installation directory <install_directory>/sw/streamline/gator/daemon/
- https://github.com/ARM-software/gator. This site is the official distribution channel for all gator releases,and contains the latest source updates between Arm Development Studio releases.

The version of gatord running on the target must be compatible with the version of Streamline that you are using. Use the same version of gatord as the version of Streamline.

For more information, see gatord.

3. To ensure gatord has execute permission, enter the following command:

```
chmod +x gatord
```

4. Ensure that you have root privileges, if necessary, then enter the following to execute gatord:

```
./gatord
```

By default, gatord uses port 8080 for communication with the host, but you can specify the port by launching gatord with the port number as a parameter. For example:

```
./gatord -p 5050
```

Next steps

- Capture a profile of your application as described in the Arm Streamline User Guide.
- To stop gatord at the end of a capture, press Ctrl+C.

2.4 System requirements for SPE support

When using the Statistical Profiling Extension (SPE) support in Streamline, there are some more system requirements.

- Use Linux kernel 4.16 or later. To confirm that support is available, check for the path /sys/bus/event source/devices/arm spe XX.
- Disable kernel page table isolation for the target. To ensure that kernel page table isolation is disabled, boot the device with the command-line argument kpti=off.
- For kernel versions 4.20 and later, apply the patch at http://lkml.iu.edu/hypermail/linux/kernel/1903.3/06760.html, or upgrade to a kernel version greater than or equal to 5.1-RC5.

For more information about SPE, see Configure SPE counters in the Arm Streamline User Guide.

2.5 gatord

To communicate with the target, Streamline requires a daemon, called gatord, to be installed and running on the target. gatord must be running before you can capture trace data.

gatord reads and processes data from applications that are running on the target. When running a headless capture, it then creates a directory, whose name ends in .apc, containing the capture data.

gatord uses the perf API to collect performance information. You can run gatord on a device with or without root permissions. Running gatord on a device with root permissions supports systemwide data collection, including profiling all applications and the kernel. When run as non-root user, gatord is limited to capturing processes that you have permission to profile. These processes are usually running as the same user.



System-wide data collection using non-root gatord falls back to /proc polling, which is deprecated. To perform system-wide data collection, use root gatord.

gatord has some restrictions, for example:

- It polls the following Linux counters every 100ms, instead of every 1ms or when they change because files in the /proc or /sys filesystem are read:
 - Memory
 - Disk I/O
 - Network

This rate is fixed and overrides the sample rate that is specified in the **Capture and Analysis Options** dialog box.

• When using gatord, the Memory: used counter does not contain per-process information. As a result, memory statistics are not available in **Processes** mode.

2.5.1 gatord command-line options

gatord must be running before you can capture trace data. The command-line options configure how gatord captures events and how it communicates with Streamline running on your host.

gatord has two modes of operation:

Daemon mode (the default mode)

Sends captured events to a host running Streamline.

Local capture mode

Writes the capture to a file then exits.

To enable this mode, specify an output directory with the --output flag.

Arguments available to all modes:

Option	Description
-h,help	Lists all the available gatord command-line options.
-c,config-xml <config_xml></config_xml>	Specify the path and filename of the configuration.xml file that defines the capture options. In daemon mode, the list of counters is written to this file. In local capture mode, the list of counters is read from this file.
-e,events-xml <events_xml></events_xml>	Specify the path and filename of the events.xml file. events.xml defines all the counters that Streamline collects during the capture session.
-E,append-events-xml <events_xml></events_xml>	Specify the path and filename of the events.xml file to append.
-P,pmus-xml <pmu_xml></pmu_xml>	Specify the path and filename of the pmu.xml file to append.
-v,version	Print version information.
-d,debug	Enable debug messages.
-A,app <cmd> <args></args></cmd>	Specify the command to execute when the capture starts. This argument must be the last argument that is passed to gatord. All subsequent arguments are passed to the launched application.
-k,exclude-kernel <yes no></yes no>	Specify whether to filter out kernel events from the perf results.
-S,system-wide <yes no></yes no>	Specify whether to capture the whole system. In daemon mode, no is only applicable whenallow-command is specified. In this mode, you must enter a command in the Start view. Requires kernel events to be enabled in Capture and Analysis Options of Streamline, or by settingexclude-kernel no. Defaults to yes, unlessapp,pid, orwait-process is specified.
-u,call-stack-unwinding <yes no></yes no>	Enable or disable call stack unwinding. Defaults to yes.

Option	Description
-r,sample-rate <none low normal high></none low normal high>	Specify the sample rate for the capture. The frequencies for each sample rate are:
	• high = 10kHz
	• normal = 1kHz
	• low = 100Hz
	none = the lowest possible rate
	Defaults to normal.
-t,max-duration <s></s>	Specify the maximum duration that the capture can run for in seconds. Defaults to 0, which means unlimited.
-f,use-efficient-ftrace <yes no></yes no>	Enable efficient ftrace data collection mode. Defaults to yes.
-w,app-cwd <path></path>	Specify the working directory for the application that gatord launches. Defaults to the current directory.
-x,stop-on-exit <yes no></yes no>	Stop the capture when the launched application exits. Defaults to no, unlessapp,pid, orwait-process is specified.
-Q,wait-process <command/>	Wait for a process that matches the specified command to launch before starting the capture. Attach to the specified process and profile it.
-Z,mmap-pages <n></n>	The maximum number of pages to map per mmaped perf buffer is equal to <n+1>. n must be a power of two.</n+1>
-O,disable-cpu-onlining <yes no></yes no>	To not switch on CPU cores that are offline to read their information. This option is useful for kernels that fail to handle this action correctly, for example they reboot the system. Defaults to no.
-F,spe-sample-rate <n></n>	Specify the SPE periodic sampling rate. The rate, <n>, is the number of operations between each sample, and must be a nonzero positive integer. The hardware specifies the minimum rate. Values below this threshold are ignored and the hardware minimum is used instead.</n>

Arguments available in daemon mode only:

Option	Description
-p,port <port_number> uds</port_number>	Set the port number that gatord uses to communicate with the host. The default is 8080.
	If you use the argument uds, the TCP socket is disabled and an abstract Unix domain socket is created. This socket is named streamline-data. If you use Android, creating a Unix domain socket is useful because gatord is usually prevented from creating a TCP server socket.
	Alternatively, you can connect to localhost: <local_port> in Streamline using:</local_port>
	adb forward tcp: <local_port> localabstract:streamline-data</local_port>

Option	Description
	Allows you to run a command on the target during profiling. The command is specified in the Start view.
	Caution: If you use this option, an unauthenticated user could run arbitrary commands on the target using Streamline.

Arguments available to local capture mode only:

Option	Description
-s,session-xml <session_xml></session_xml>	Specify the session.xml file that the configuration is taken from. Any additional arguments override values that are specified in this file.
-o,output <apc_dir></apc_dir>	Specify the path and filename of the output directory for a local capture. The directory path will be appended with the extension .apc if it is not already the case.
-i,pid <pids></pids>	A comma-separated list of process IDs to profile.
-C,counters <counters></counters>	A comma-separated list of counters to enable. You can specify this option multiple times. An event code and a slot identify most hardware counters. To specify the counter for a particular slot, pass:
	counters <device>_cnt<s>:<e></e></s></device>
	Where:
	<device> is the prefix that identifies the device type.</device>
	• <s> is the slot number.</s>
	<e> is the event code.</e>
-X,spe <id>[:events=<indexes>][:ops=<types>] [:min_latency=<lat>]</lat></types></indexes></id>	Enable the Statistical Profiling Extension (SPE).
	Where:
	• <id>is the name of the SPE properties that are specified in the events.xml or pmus.xml file. It uniquely identifies the available events and counters for the SPE hardware.</id>
	• <indexes> is a comma-separated list of event indexes to filter the sampling by. A sample is only recorded if all events are present.</indexes>
	• <types> is a comma-separated list of operation types to filter the sampling by. If a sample is any of the types in <types>, it is recorded. Valid types are LD for load, ST for store and B for branch.</types></types>
	• <lat> is the minimum latency. A sample is only recorded if its latency is greater than or equal to this value. The valid range is [0,4096).</lat>

Argument usage examples

• Use --pmus-xml and --append-events-xml to add support for a new PMU without having to rebuild gatord.

--pmus-xml specifies an XML file that defines a new PMU to add to the list of PMUs that gatord has built-in support for. The list of built-in PMUs is defined in pmus.xml, which is in the gatord source directory.

--append-events-xml specifies an XML file that defines one or more event counters to append to the events.xml file. This option allows you to add new events to gatord without having to rebuild gatord or to entirely replace events.xml.

The events.xml file must include the XML header and elements that are shown in the following example:

The Instructions Executed counter is configured in slot 0 as:

```
--counters ARMv8_Cortex_A53_cnt0:0x08
```

To configure the cycle counter, specify --counters <device>_ccnt. For example:

```
--counters ARMv8_Cortex_A53_ccnt
```

Other counters do not have event codes and are identified only by name. For example:

```
--counters PERF_COUNT_SW_PAGE_FAULTS
```

2.6 Capture data locally on a target

You can run gatord from the command line to configure the counters and capture data locally on your target.

Procedure

Start gatord specifying:

- The location for the output file with --output.
- Optionally specify which counters to use with either --config-xml or --counters.

```
./gatord --output <path> --counters <counters>
```

Results

gatord captures a profile of all the processes running on your system, and writes the data to the specified location.

Next steps

Copy the .apc directory into the Streamline capture directory. This directory is usually <home>/
Documents/Streamline.

Related information

Creating a configuration.xml file

2.7 Support for Arm CoreLink tools

Streamline supports various Corelink interconnect parts, including: CCI-400, CCI-500, CCN, CMN-600, L2C-310, SMMUv3, and DSU.

Profiling these devices relies on support for the correct PMU driver being present and enabled in the Linux kernel. Ensure you are using a version that supports your hardware, and that you have the correct configuration options enabled in the kernel.

2.8 Using Streamline with Arm NN

Streamline supports capturing profiling information from Arm NN enabled applications. This feature enables you to collect performance counters from supported Arm[®] Ethos[™] NPUs and performance data from the Arm NN library. To profile an Arm NN application, gatord must first see which events are available in the running application. Streamline can then capture a profile as normal.

Before you begin

- Build your application against Arm NN version 20.08 or later. See https://github.com/ARM-software/armnn for more information.
- When you create the runtime in your application code, you must set
 options.m_ProfilingOptions.m_EnableProfiling = true for the options passed to
 IRuntime::Create.
- Enable timeline profiling by setting options.m_ProfilingOptions.m_TimelineEnabled = true.

```
// Create Arm NN runtime
IRuntime::CreationOptions options; // default options
options.m_ProfilingOptions.m_EnableProfiling = true;
options.m_ProfilingOptions.m_TimelineEnabled = true;
IRuntimePtr run = IRuntime::Create(options);
```

Procedure

1. Start gatord in daemon mode as described in Set up your target.



Local capture mode is not available because gatord does not know which events are available yet.

- 2. Run your application.
- 3. Configure counters and Capture a Streamline profile as described in the Arm Streamline User Guide.



To get the timeline data, you must start your application again after starting the capture.

3 Customize your Streamline report

This chapter explains how to add support for a new CPU, or an uncore peripheral outside of the CPU, to Streamline.

3.1 Add a CPU to Streamline

Customize your Streamline reports with support for custom CPU Performance Monitoring Units (PMUs).

Procedure

- Create an events-<processor_name>.xml file and save it in <Ds_install_directory>/sw/ streamline/gator/daemon/.
- 2. Include the following in the file:

```
<counter_set name="<ID>_cnt" count="<NEVENTS>"/>
<category name="<NAME>" counter_set="<ID>_cnt" per_cpu="no">
    <event .../ >
</category>
```

<ID> is a string that can contain letters, numbers, and underscores.

<NEVENTS> is the maximum number of counters in the hardware.

If the number of events is unlimited, the <counter_set> element and the counter set="<ID> cnt" attribute are not required.

- 3. Add a <pmu> element to pmus.xml .

 See the comment at the top of the pmus.xml file for the required attributes.
- 4. Rebuild gatord.

3.2 Add an uncore peripheral to Streamline

Customize your Streamline reports with support for custom uncore peripheral Performance Monitoring Units (PMUs).

Procedure

- 1. Create an events-<peripheral_name>.xml file and save it in <Ds_install_directory>/sw/streamline/gator/daemon/.
- 2. Include the following in the file:

```
<counter_set name="<ID>_cnt" count="<NEVENTS>"/>
<category name="<NAME>" counter_set="<ID>_cnt" per_cpu="no">
    <event .../ >
</category>
```

<ID> is a string that can contain letters, numbers, and underscores.

<NEVENTS> is the maximum number of counters in the hardware.

- If the number of events is unlimited, the <counter_set> element and the counter_set="<ID>_cnt" attribute are not required.
- 3. Add an <uncore_pmu> element to pmus.xml.

 See the comment at the top of the pmus.xml file for the required attributes.
- 4. Rebuild gatord.

3.3 Contributing CPU and peripheral support

The gator daemon is an open-source component, licensed under the GPLv2 license, and published on GitHub. We are willing to accept pull requests from external developers to add support for custom Arm cores and supporting uncore peripherals.

The gator daemon is in this repository https://github.com/ARM-software/gator/, where you can also find the contributing guidelines.

4 Troubleshooting Common Arm Streamline Issues (Linux)

Troubleshoot known Streamline issues.

4.1 Troubleshooting target connection issues

Use these solutions for common target connection issues.

Problem	Solution
Error message generated:	Make sure gatord is running on your target. Enter the following command in the shell of your target:
In: Streamline/gator/kEADME.md. If connecting over WiFi, please try again or	ps ax grep gatord
	If this command returns no results, gatord is not active. Start it by navigating to the directory that contains gatord and entering the following command:
	sudo ./gatord &
	Try connecting to the target again.
	If gatord is active and you still receive this error message, disable any firewalls on your host machine that might interfere with communication between host and target.
Error message generated:	Make sure that you have correctly entered the name or IP address of the target in the Enter target details field. If you have entered a
Unknown host	name, try entering an IP address instead.
When using event-based sampling, Streamline fails to find the PMU.	The PMU on your hardware might not be correctly configured to allow the processor interrupts necessary for Streamline to use event-based sampling. Test on alternate hardware or disable event-based sampling in the Counter Configuration dialog box.

Problem	Solution
The target is running a firewall, which prevents Streamline from connecting to gatord.	There are several possible ways to resolve this issue:
	Update the firewall to allow connections to gatord, which defaults to using port 8080.
	Use local captures.
	If the target accepts SSH connections, you can establish an SSH tunnel by using the ssh command on the host. For example:
	ssh <user>@<target> -L 8080:localhost:8080 -N</target></user>
	In this example, replace <user> with the username to log in as and <target> with the hostname of the target. On the target, use localhost as the hostname.</target></user>
	Note: An SSH tunnel requires extra processing on the target.
	Reverse SSH tunnels are also possible by running ssh from the target to the host. For example:
	ssh <user>@<host> -R 8080:localhost:8080 -N</host></user>

4.2 Troubleshooting gatord issues

Use these solutions for issues related to gatord.

Problem	Solution
Kernel version before 4.6 with CONFIG_CPU_PM enabled produces invalid results. For example, counters not showing any data, large spikes, and non-sensible values for counters. This issue is due to the kernel PMU driver not saving state when the processor powers down, or not restoring state when it powers up.	Upgrade to the latest version of the kernel, or apply the patch found at https://git.kernel.org/pub/scm/linux/kernel/git/torvalds/linux.git/commit/?id=da4e4f18afe0f3729d68f3785c5802f786d36e34. This patch applies cleanly to version 4.4, and it might also be possible to back port it to other versions. If you apply the patch, you might also require the patch at https://git.kernel.org/pub/scm/linux/kernel/git/torvalds/linux.git/commit/?id=cbcc72e037b8a3eb1fad3c1ae22021df21c97a51.
An Oops occurs when a processor is offlined.	The fix was merged into mainline in 3.14-rc5, see https://git.kernel.org/pub/scm/linux/kernel/git/tip/tip.git/commit/?id=e3703f8cdfcf39c25c4338c3ad8e68891cca3731, and has been backported to older kernels (3.4.83, 3.10.33, 3.12.14, and 3.13.6).
dmesg output:	Update to the latest Linux kernel.
CPU PMU: CPUx reading wrong counter -1	
Scheduler switch resolutions are on exact millisecond boundaries.	Update to the latest Linux kernel.

5 Advanced target setup information (Linux)

This appendix provides extra configuration information beyond the standard setup.

5.1 Kernel configuration menu options

You must enable certain kernel configuration options to run Streamline.

The following menuconfig menus have options that are required for Streamline:



- If these options are not set correctly, you must change them and rebuild your kernel. If they are set correctly, you are ready to build and install the gator driver.
- The location of these options might change between releases. If so, use the search option in menuconfig to find them.
- Extra options are required to enable Arm[®] Mali[™] GPU support.

General Setup

Enable the **Profiling Support** option <code>config_profiling</code>, and the **Kernel performance events** and counters option <code>config_perf_events</code>. <code>config_perf_events</code> is required for kernel versions 3.0 and later. Enable the **Timers subsystem** > **High Resolution Timer Support** option <code>config_High_Resolution</code> timers.

Kernel Features

The Enable hardware performance counter support for perf events option config_hw_perf_events. config_hw_perf_events is required for kernel versions 3.0 and later. If you are using Symmetric MultiProcessing (SMP), enable the Use local timer interrupts option config_local_timers. If you are running on Linux version 3.12 or later, the config_local_timers option is not necessary.

CPU Power Management

Optionally enable the **CPU Frequency scaling** option <code>config_cpu_freq</code> to enable the CPU Freq **Timeline** view chart. <code>gatord</code> requires kernel version 2.6.38 or greater to enable this chart.

Kernel hacking

If other trace configuration options are enabled, the **Trace process context switches** and events option <code>config_enable_default_tracers</code> might not be visible in <code>menuconfig</code> as an option. Enabling one of these other trace configurations, for example <code>config_generic_tracer</code>, <code>config_tracing</code>, or <code>config_context_switch_tracer</code>, is sufficient to enable tracing. Optionally enable the **Compile the kernel with debug info** option <code>config_definition</code> is only required for profiling the Linux kernel.



Kernel versions before 4.6, with <code>config_cpu_pm</code> enabled, produce invalid results. For example, counters not showing any data, large spikes, and non-sensible values for counters. This issue is due to the kernel PMU driver not saving state when the processor powers down, or not restoring state when it powers up. To avoid this issue, upgrade to the latest version of the kernel, or apply the patch found at https://git.kernel.org/pub/scm/linux/kernel/git/torvalds/linux.git/commit/?id=da4e4f18afe0f3729d68f3785c5802f786d36e34. This patch applies cleanly to version 4.4, and it might also be possible to back port it to other versions. If you apply the patch, you might also require the patch at https://git.kernel.org/pub/scm/linux/kernel/git/torvalds/linux.git/commit/?id=cbcc72e037b8a3eb1fad3c1ae22021df21c97a51.

5.2 Profile the Linux kernel

To ensure the statistics that the kernel generates align with source code in the Analysis Reports, include the kernel in the **Program Images** section in the **Capture and Analysis Options** dialog box. Before you can include the kernel in the **Program Images** section, you must build a version of vmlinux with kernel debug information enabled.

Procedure

- 1. Navigate to the kernel build directory.
- 2. Enter the following command to enable you to change menuconfig options:

- 3. In the **Kernel Hacking** menu, select the **Compile the kernel with debug info** option. This option enables the config debug info kernel option.
- 4. Enter the following command to build a new vmlinux image:

make -j5 ARCH=arm CROSS_COMPILE=<cross_compiler_directory>/bin/arm-linuxqnueabihf- uImage



You can profile a driver by either statically linking it into the kernel image or by adding the module as an image in the **Capture and Analysis Options** dialog box.

- 5. Open the **Capture and Analysis Options** dialog box.
- 6. Click the Add ELF image... button in the Program Images section.
- 7. Navigate to your vmlinux file and select it.
- 8. Click OK.
- 9. Start a new capture session.

Related information

Kernel configuration menu options on page 22

5.3 Build gatord yourself

Build gatord yourself to apply patches for bug fixes or add support for new features.

About this task



It is not possible to build gatord on a Windows host.

Procedure

- Either download the gatord source from the daemon directory in https://github.com/ARM-software/gator, or copy the source that is supplied in <DS_install_directory>/sw/streamline/gator/daemon/.
- 2. Follow the instructions in the README.md file in the gator directory.

Related information

Set up your target on page 9

5.4 Add support to gatord for a new CPU or perf PMU

There are two methods for adding support for a new CPU or perf PMU to gatord. One that requires rebuilding gatord, and one that does not.

- Perf support in Linux for the PMU is required because gatord uses perf to read the hardware counters.
- Check the perf PMUs supported by your kernel by running:



ls /sys/bus/event_source/devices/

If ARMv7_Cortex_A<xx>, CCI_400, or cnn are listed, then A<xx>, CCI-400, or CNN respectively are supported.

- Only XML changes are required, no code changes are necessary.
- Rebuilding gatord after the XML changes is recommended but not required because you can pass PMUs and events to gatord on the command line.

Make the following changes, then rebuild gatord:

- 1. Add a line to <install_directory>/sw/streamline/gator/daemon/pmus.xml describing the new PMU. For CPUs, the following information is required:
 - The CPU Implementer and Primary part number from the Main ID Register.

- The number of generic hardware counters that can be selected simultaneously.
- Optionally, set the perf PMU name of the CPU to ensure correct operation in multi-PMU heterogenous CPU implementations, such as big.LITTLE™ or DynamIQ.
- 2. Create an events XML file, named events-<xxx>.xml in the gatord source directory that defines the events that the new PMU generates. Exclude the XML header and <events> element. See the Cortex®-A15 events XML file, cps_install_directory/sw/streamline/gator/daemon/events-Cortex-A15.xml for an example.

Alternatively, to add support without having to rebuild gatord, do the following:

1. Create an events XML file that defines the events that the new PMU generates. This file must include the XML header and <events> element, for example:

2. Create an XML file that defines information about the new PMU. For the required format, see the gator pmus.xml. For example:

```
<?xml version="1.0" encoding="UTF-8"?>
<pmus>
    <pmu pmnc_name="ARMv7_Cortex_A9" cpuid="0x41c09" core_name="Cortex-A9"
    pmnc_counters="6"/>
</pmus>
```

- 3. Copy these files to the target and restart gatord using the following flags:
 - -E to specify the location of the events XML file. This flag causes the events to be appended to the list of events that gatord supports.
 - -P to specify the location of the PMU XML file. This option causes the new PMU to be added to the list of PMUs defined in pmus.xml that gatord has built-in support for.

Related information

Build gatord yourself on page 24 gatord command-line options on page 12